

From Forest Nursery Notes, Winter 2012

293. Water supply and quality: the basics. Bilderback, T., Dole, J., and Sneed, R.
American Nurseryman June 2011, p. 12-16, 18-19. 2011.

Water Supply and Quality: The Basics

Nothing is more basic to plant health than water. Knowing how to evaluate and adjust your water supply—and its quality—will help to yield quality crops.

BY TED BILDERBACK, JOHN DOLE AND RONALD SNEED

A sufficient quantity of high-quality water is extremely important for the production of nursery crops. Daily irrigation is required during most of the growing season for container crops that are predominantly grown in bark-based potting substrates. This need for frequent irrigation requires careful planning and management to ensure that operations have sufficient water to maintain adequate supplies for crop production. In addition, many container nurseries capture and recycle irrigation water, not only to protect the environment but also to provide adequate irrigation supplies for production.

High-quality water is required for a number of reasons, including the prevention of plugging of nozzles, staining of foliage and containers, excessively high substrate salt levels, and improper substrate pH. Water supplies containing iron and bicarbonates frequently require pre-treatment before use. Sediment must be filtered out of water supplies to prevent wear and clogging of irrigation systems.

To improve the quality of recycled water, nurseries may use a variety of landscape features including vegetative buffers, grassed waterways and collection structures to slow velocity, filter and direct movement of runoff to collection basins. Various disinfection practices may be installed at nurseries that recycle irrigation water.

Irrigation water supply

Most nursery crops grown in 1- to 5-gallon (4 to 14 L) containers are irrigated with overhead sprinklers. A single sprinkler nozzle will require 4 to 7 gallons (15 to 26 L) per minute (GPM) for proper performance. For container nurseries, a minimum of a 30-day supply of one acre-inch (27,154 gal/acre or 102.8 m³/ha) should be planned. Another common recommendation is to plan for 5 to 10 acre-feet of irrigation water annually per acre (156,000 to 31,200 kL/ha) of nursery stock. If container stock is irrigated for 163 days a year at the rate of 1 acre-inch per day, approximately 4.5 million gallons per acre (43,088 kL/ha) will be required annually. This is equivalent to 14 acre-feet of water per acre (43,680 kL/ha) of nursery stock.

Therefore, for site development and water supply planning purposes, 14 acre-feet of water per acre (43,680 kL/ha) of nursery production area should provide adequate water supplies. In reality, nurseries may need only one-half this amount, using a square irrigation design which can reduce daily irrigation requirement to one-half-acre-inch (9 kL/ha) compared to an acre-inch (18 kL/ha) per day for less efficient systems. Furthermore, recharge from rainfall, runoff, wells or streams can reduce the amount of storage needed.

Surface water storage structures are the primary source of irrigation water at most container nurseries. Wells are often used to recharge and resupply water in storage structures. An estimate of the storage basin capacity can be made by multiplying the average width, length and depth of the basin to determine the approximate volume in cubic feet and multiplying the result by 7.5 (7.5 gallons = 1 cubic foot). If metric is used, 264 gallons = 1 m³. Assuming one-

half-inch (1.3 cm) of water is applied per acre of nursery production area per day, dividing the storage capacity by 13,500 gallons (129.3 kL)/acre provides the approximate number of irrigation days for 1 acre (0.4 ha) available from the stored supplies. The number of days for 1 acre divided by the production area in acres gives an estimate of the number of days of irrigation available for the entire nursery. This calculation does not account for evaporation and all other losses of water from the basin, but is useful for planning purposes.

Disinfection and treatment of recycled water

Many wholesale nurseries capture and recycle irrigation water runoff to provide enough water for their container crops. However, recycled irrigation supplies can be a source of pathogenic fungal species, such as *Pythium*, *Phytophthora*, and possibly other diseases. Recycled water also contains nutrients that support the growth of microorganisms. Therefore, many nurseries have installed irrigation water disinfection systems to remove algae, iron bacteria and other organisms that can create problems for the plants or the irrigation system.

The most common disinfection systems are liquid and/or gas chlorination systems. Other types of disinfection systems include bromination (primarily for propagation), Cu ion generators, hydrogen peroxide, ultraviolet light lamps and ozonation. All of these disinfection techniques require relatively clean water to be effective; thus pretreatment filtration with screen or disk filters is necessary for overhead sprinkler irrigation, and sand media filtration is usually necessary for low-volume drip irrigation systems. Depending upon the amount of organic materials in the irrigation water supply,

you may need a filter both before and after chlorination to remove free-floating debris.

Chlorine is typically used as a disinfectant and oxidizing agent. Chlorine oxidizes ferrous iron (Fe^{2+}) to ferric (Fe^{3+}). As a disinfectant, chlorine kills algae, bacteria and other organisms in the water supply. Chlorination also eliminates the energy source for iron bacteria. If large amounts of algae are present in the irrigation water, filters are necessary post-treatment to remove the debris to prevent plugging of irrigation nozzles.



As a disinfectant, chlorine kills algae, bacteria and other organisms in the water supply. Chlorination also eliminates the energy source for iron bacteria. Chlorine gas is injected from gas cylinders, which should be kept in a locked wire cage with a roof covering to reduce potential human exposure to gas chlorine when changing cylinders.

COURTESY OF TED BILDERRACK

Injecting chlorine into existing irrigation lines requires some retrofitting and installation of backflow devices in the irrigation system, normally near the pump discharge. To be effective, chlorine requires adequate contact time in the irrigation water—about 1 minute at a minimum of 0.5 ppm (mg L) active chlorine. This can be accomplished with storage tanks, swirl chambers or extra loops in the irrigation lines. To reduce the amount of chlorine needed, organic residue should be filtered before the chlorine injector. Usually sand media filters are installed. A minimum of two media filters are recommended, allowing one filter to be backwashed while the other filter operates during irrigation.

Chlorine gas is injected from gas cylinders. Gas is more effective than liquid chlorine but is also considerably

more dangerous and may require community notification and even evacuation plans for storage of large quantities of chlorine gas. The greatest danger occurs when cylinders have to be changed, particularly if the cylinders are housed in a building. A locked wire cage with a roof covering is preferable to reduce potential human exposure to gas chlorine when changing gas cylinders (photo, below). Employee training and safety instructions are essential if gas chlorination is used.

Liquid chlorine injection is a safer alternative. Liquid chlorine (16 percent

therefore alkaline water supplies have drastic effects on availability of nutrients in organic potting substrates.

Poor water quality may lead to excessively high salts and pH extremes in the substrate, nutritional problems, fouling of irrigation devices and algae growth. Furthermore, high concentrations of sediment, iron and bicarbonates plug low-volume nozzle orifices. Therefore, nursery and greenhouse producers should regularly monitor irrigation water sources for electrical conductivity (EC), pH and nutrient content. Table 1 (page 14) lists the most important quality factors to consider for irrigation water for nursery crop use. If test results are above the recommended upper limit for a particular factor, it does not necessarily mean the water source is unacceptable; rather, water treatment, a change in management or a change in the fertilization program may be required.

• pH and alkalinity in water supplies

The recommended range of irrigation water pH and substrate solution pH for container production depends on the crop species being grown. The generally accepted pH range is 5.4 to 6.8 for irrigation water, and 5.2 to 6.3 for the substrate solution. Availability of micronutrients such as iron, manganese, zinc, copper and boron and future plant growth can be severely reduced by high substrate and irrigation water pH above 6.8. High pH water can also cause salts to precipitate out of fertilizer stock tanks and can also reduce the efficacy of pesticides.

Acid treatment of irrigation water may be needed for container production, if water pH and alkalinity are too high. Alkalinity is defined as the sum of carbonate (CO_3^{2-}) and bicarbonate (HCO_3^-) ions in solution. High alkaline waters can occur throughout the world.

Water that has high carbonate and bicarbonate levels above 2.0 meq (100 ppm) may require acidification treatment. However, the specific amount of water alkalinity that may be a problem will depend on the crop production time, container size and crop species. The increase in media pH due to alkalinity will not be a problem for many bedding plants due to short crop times; however, the pH increase will be a problem for the long-term production of many container-grown plants and cut-flower crops. While plugs are

sodium hypochlorite) is usually purchased in 50 gallon (190 l) drums. A variable ratio injector should be used, because 16 percent sodium hypochlorite loses strength over time and the injection rate must be increased. Free chlorine is checked using a swimming pool test kit at the end of an irrigation line or riser and if the test sample turns slightly pink, indicating 1 to 3 ppm (mg L), sufficient chlorine has been injected.

Water quality

As mentioned in the introduction, high-quality irrigation water is especially important for greenhouse and nursery production because impurities coat leaf surfaces, reduce plant growth and decrease the marketability of crops. Additionally, many soilless substrates lack the buffering capacity of soils, and

Table 1. Nutrient and Chemical Ranges Occurring for Water, Substrates and Plant Tissue Parameters in Woody Ornamental Crop Production

Quality Factor	Irrigation Water ¹ (BMP's)	Substrate Leachate ² (PourThru)	Plant Tissue ³
pH	5.4-6.8	5.2-6.3	-
Conductivity	0.2-2.0 mmhos/cm (dS/m)	0.5-2.0 mmhos/cm (dS/m)	-
Total dissolved salts	<1000 ppm	<1400 ppm	-
Bicarbonate	<100 ppm or <2 meq/l	-	-
Alkalinity	<2 meq/l	-	-
(carb. + bicarb.)	<100 ppmCaCO ₃	-	-
[1 meq = 50 ppm]			
TC	<2 meq/l	-	-
Hardness	150 ppm or 3 meq/l (Ca + Mg)	-	-
SAR	<10 meq/l		
Na	<3 meq/l or <50 ppm	<50 ppm	0.01-0.1%
Chlorides	<70 ppm	<70 ppm	50-200 ppm
N		25-150 ppm	2.0-3.5%
NO ₃ -N	<10 ppm	50 ppm	-
NH ₄ -N	1-2 ppm	50 ppm	-
P	<1 ppm	1-5 ppm	0.2-0.5%
K	<10 ppm	<100 ppm	1.1-2.0%
Ca	<60 ppm	40-200 ppm	1.0-2.0%
Mg	<6-24 ppm	10-50 ppm	0.3-0.8%
S	<24 ppm	75-125 ppm	0.2-0.7%
Fe	0.2-4.0 ppm	0.3-3.0 ppm	35-250 ppm
Mn	<0.5-2.0 ppm	0.02-3.0 ppm	50-200 ppm
Zn	<0.3 ppm	0.3-3.0 ppm	20-200 ppm
Cu	<0.2 ppm	0.01-0.5 ppm	6-25 ppm
B	<0.5 ppm	0.5-3.0 ppm	6-75 ppm
Mo	<0.1 ppm	0.0-1.0 ppm	0.1-2.0 ppm
Al	0.05-0.5 ppm	0.0-3.0 ppm	<300.0 ppb
Fl	<1.0 ppm		

1. Ranges that generally do not require water treatment.

2. Recommended concentration in leachate collected from substrate. See the following section "Monitoring Container Leachate For EC And pH"

3. Desired concentration in leaf tissue samples

Water Supply & Quality: The Basics

Continued from page 13

a short-term crop, they are particularly sensitive to high media pH due to the small container volume. High water alkalinity can cause the pH of plugs to rapidly rise to unacceptable levels. Finally, some crop species such as azaleas (*Rhododendron*) or blue hydrangeas (*Hydrangea*), require low media pH and will be difficult to produce with high water alkalinity. Regardless of the level, alkalinity is too high anytime it causes the media pH to rise to an unacceptable level.

Acidification reduces the amount of these ions in water, resulting in the

formation of carbon dioxide and water. Sulfuric (H₂SO₄), phosphoric (H₃PO₄), nitric (HNO₃), or citric (H₃C₆H₅O₇) acids are commonly injected. In addition to cost, ease of use and plant nutrients, safety is a factor in deciding which acid to use. Citric acid, 75 percent phosphoric acid and 35 percent sulfuric acid are relatively safe to work with, compared to the 67 percent nitric acid. Nitric acid is very corrosive and can cause serious injury to exposed tissue, especially eyes. Nitric acid can also fume during handling, requiring precaution to avoid breathing fumes. (For detailed guidelines on acid treatment of irrigation supplies, see information leaflets available at www.ces.ncsu.edu/depts/hort/floriculture/crop/crop_water.htm).

Several options are available to control low to moderate alkalinity

through cultural practices. Producers that mix their own media can add less lime to the media. For growers who use basic fertilizers, such as calcium nitrate and potassium nitrate, the water pH and alkalinity can be on the low end of the recommended range to prevent the media pH from increasing to unacceptable levels during production. Growers who use acidic fertilizers, especially in warm climates, can readily use water with the pH and alkalinity in the center or upper part of the recommended range for an individual species.

Producers can rotate among acidic and basic fertilizers. While many pre-mixed fertilizers have relatively high ammonium levels and are acidic, basic nitrate-based fertilizers are available. In addition, growers can combine potassium nitrate and calcium nitrate to make

their own basic fertilizer. Unfortunately, high ammonium fertilizers are not feasible in some situations, which limits the ability of growers to control media pH through fertilizer choice. High ammonium fertilizers should not be used when the media temperature is below 55°F (13°C) due to slow conversion of ammonium to nitrates by nitrifying bacteria in the media. Ammonium can also produce excessive growth, which can counteract height control measures for some crops.

• **Electrical conductivity**

Electrical conductivity (EC) is a measure of the total dissolved salts (TDS) in any solution. A high concentration of salts provides an osmotic potential that reduces water uptake and increases the uptake of unwanted ions by plants. This results in various symptoms such as wilting, stunting and the necrosis of leaf margins. Younger seedlings tend to be more sensitive to high salt levels than other crops, so EC monitoring is especially important for plug production of seedlings and in propagation houses.

Water's ability to conduct an electrical current is directly related to the concentration of dissolved salts. Pure

water is a relatively poor conductor of electricity, whereas salty water is a good conductor. The greater the EC, the more dissolved salts are present in solution. EC is commonly expressed in units of millimhos per centimeter (mmohs/cm) or deciSemens per meter (dS/m), which are numerically equivalent. The soluble salt level in the irrigation water should ideally be under 0.75 dS/m for seedlings, and less than 2.0 dS/m for nursery crops. Although EC is an indicator of total dissolved salts, it offers little information on what ions are present, and no information on the concentrations of each element. Moderately high EC (0.75 dS/m) during summer months in water supplies might suggest the presence of nitrogen or other nutrients. Under drought conditions, sulfates and chlorides become concentrated in water supplies, rather than essential nutrients. Only laboratory analysis can confirm what management strategies need to be employed.

• **Monitoring container leachate for EC and pH**

Monitoring container leachates can help growers take preventive steps to reduce possible damage to roots due to high electrical conductivity before visible symptoms occur. Some nurseries

monitor EC's on a weekly basis, to determine how they will irrigate or fertigate each zone the following week. If the leachate EC is elevated during nursery crop production, more water will be applied the following week to leach out salts. If ECs are low, the irrigation volume will be decreased in those zones the following week. The Southern Nursery Association Best Management Practices manual recommends that growers monitor EC at least once a month. Data from monitoring ECs can provide valuable insight into the fertilization program, and pre-empt plant growth problems that may arise from excess (or deficient) salts. Monitoring on a frequent basis allows for sound management decisions—the more frequent the monitoring, the better the quality of the data and the more likely that production problems will be caught in a timely fashion.

Nutrient concentrations, pH and electrical conductivity levels can be monitored by using the pour-through extraction procedure. The procedure requires pouring enough water over the surface of the substrate to collect approximately 2 fluid ounces (50 ml) leachate solution from containers about

Continued on page 16

It's Still Acers to Zelkova, Plus 20 New Varieties!

We've nearly doubled our ornamental seedling and cutting liner varieties.

SEE ALL OF OUR NEW OFFERINGS, PLUS CURRENT AVAILABILITIES AT
WWW.WILLAMETTENURSERIES.COM

OUR CUSTOMERS COME TO US FOR OUR ROOTSTOCK.
THEY COME BACK FOR OUR SERVICE.



**WE SPECIALIZE
IN UNDERSTOCK
FOR FLOWERING,
FRUITING & SHADE.**

OUR ROOTS ARE IN THE
WILLAMETTE VALLEY...
OUR SERVICE IS
HOME-GROWN, TOO.



503-263-6405 TOLL FREE 1-800-852-2018 EMAIL: WILLAMETTE@CANBY.COM

Water Supply & Quality: The Basics

Continued from page 15

30 minutes to 2 hours after irrigation, and collecting the effluent that comes out of the bottom of the container.

Alternatively, growers can collect solution that drips out of the container 30 minutes to 2 hours after irrigating. The BMP manual for nurseries suggests minimal levels for EC should range from 0.2 to 0.5 dS/m for controlled release fertilizers (CRFs) and 0.5 to 1.0 dS/m for liquid feed or combinations of CRFs and liquid. Maximum EC levels for most plant species grown in pine-bark based substrates should not exceed 2.0 dS/m. Levels greater than 7.8 dS/m will generally result in rapid crop injury and immediate leaching is required.

To test the leachate solution, a grower needs to purchase a pH and conductivity meter. Inexpensive glass electrode pH pens and conductivity pens provide accurate results and can save thousands of dollars in crop losses. Sending the leachate solution for laboratory analysis at least once during the growing season is a good practice to determine actual

nutrient levels in the container and correct them if needed. Leachate analysis and plant tissue analysis are the best diagnostic steps to determine nutritional disorders. Other methods, such as 1:2 substrate:water dilution, press test and saturated media extract can also be used, especially in greenhouse production, to determine substrate EC, pH and nutrient conditions.

• Sodium Absorption Ratio (SAR)

Greenhouse and nursery crops have minimal sodium requirements. The SAR is a calculated value that indicates the concentration of sodium relative to that of calcium and magnesium. Irrigation water having an SAR above 4 can result in root uptake of toxic levels of Na (sodium). Water containing greater than 3 meq/L sodium should not be used for overhead irrigation of ornamentals and greenhouse plants as foliar absorption of sodium can lead to sodium toxicity with sensitive species. Sodium toxicity, whether due to root absorption or foliar absorption of Na, is expressed as marginal leaf burn on older foliage.

Damage from high sodium concentration in irrigation supplies can be partially prevented by the addition of calcium. Dilution of sodium using an alternative water supply is another

method to reduce high sodium problems in water supplies. To calculate the approximate SAR of water, sodium (Na), calcium (Ca) and magnesium (Mg) concentrations are entered as meq/L in the following formula:

$$SAR = \frac{Na}{\sqrt{\frac{Ca + Mg}{2}}}$$

In the nursery, the SAR should be less than 10.

• Macro Elements

The macro elements nitrogen (N), phosphorus (P), potassium (K), calcium (Ca), magnesium (Mg) and sulfur (S) are essential for plant growth. At moderate levels, these elements do not cause production problems. The concentration of N, P and K should be evaluated as an indicator of potential contamination and alternatively sources of these nutrients in irrigation water. For example, concentrations of N or K greater than 10 ppm (mg/L), or concentrations of P greater than 1 ppm (mg/L) in ground water suggests that the water has been contaminated with a fertilizer or nutrients from other sources, such as septic systems, or from organic sources such as manures.


Concentrations of Ca, Mg and S in irrigation water should be analyzed for fertilizer requirements. Calcium and magnesium are normally found in irrigation water in the ranges given in Table 1. It is acceptable to use water containing the highest levels of Ca and Mg listed, if the amount of calcium and magnesium supplied in the fertilizer program is reduced and if the ratio of calcium to magnesium in the water source is within acceptable limits. Ideally, the calcium to magnesium ratio in the substrate solution (and in the irrigation water) should be 3 Ca to 1 Mg if expressed as meq/L or about 5 Ca to 1 Mg if expressed as ppm. If the ratio is significantly different, a deficiency may occur in the nutrient that is undesirably low. The most common problem is a low level of magnesium relative to calcium (that is, high ratio). In this case it is necessary to supplement occasionally with a Mg source, such as magnesium sulfate (epsom salts). Examine the ratio of calcium to magnesium (Ca:Mg) in the water to anticipate whether the substrate Ca:Mg will tend to shift out of the desired range.

Sulfur concentrations in irrigation water are usually less than 25 ppm (mg/L), and excessive sulfur is not normally a problem, except where acidification poses problems. Table 1 lists recom-

Continued on page 18

www.amerinnursery.com


Get Your NC Christmas Tree Association Wholesale Guide



Wholesale Trees for:

- ▲ Retail Lots
- ▲ Fundraising Groups
- ▲ Non-Profit Groups
- ▲ Garden Centers
- ▲ Churches

Call Today To Receive Your **FREE GUIDE**
1-800-562-8789



www.NCchristmastrees.com

KEEPIN' IT REAL ▲ NORTH CAROLINA FRASER FIR

Water Supply & Quality: The Basics

Continued from page 16

mended levels of sulfur for best plant growth. It is not usually necessary to add sulfur to reach these recommended levels, as sulfur is a common contaminant of many fertilizer sources. Tissue tests will confirm whether your fertilization program has sufficient sulfur.

• Micro elements

Irrigation water can contain small concentrations of aluminum (Al), boron (B), copper (Cu), fluoride (Fl), iron (Fe), manganese (Mn), molybdenum (Mo) and zinc (Zn). With the exception of Al and Fl, these elements are essential to plant growth and are required in small quantities. Aluminum in irrigation water is rarely found in concentrations high enough to lead to toxicities, and should not be a major concern for most growers. Fluoride is often added to municipal water at a concentration of 1 ppm (mg/L) to prevent tooth decay. This level is safe for most crops—but not for members of the lily family and a few other plants. Toxic levels of fluoride cause tip scorch of the older leaves.

Among the plant micronutrients

found in water, boron can be particularly troublesome. A concentration less than 0.5 ppm (mg/L) is safe for any irrigation use. A level greater than 0.5 ppm (mg/L) could lead to toxicity symptoms in boron-sensitive crops. Boron toxicity can first show up as orange-brown necrosis along the margins of older leaves. Flecking can also occur on the underside of leaves. Boron deficiency can also be a problem, particularly when soilless substrates have been overamended with lime to correct for seemingly low pH levels. In such cases, boron is complexed by Ca and therefore not available for plant growth. Excessive bud proliferation with small stunted (chlorotic) young leaves is a striking symptom often associated with B deficiency.

Other micronutrients that can be excessive in irrigation water are iron, manganese, zinc and copper. Assure that concentrations of these elements are below the levels listed in Table 1 prior to using water. Micronutrient toxicities are more likely to occur when the substrate pH is low, rendering the micronutrients more available for plant uptake. If the water contains high micronutrient concentrations, the fertilization program should be adjusted to prevent an overabundance of the elements.



A high iron concentration in irrigation water can lead to aesthetic and nuisance problems. Overhead irrigation with water containing 0.5 ppm (mg/L) or more of iron frequently results in a red-brown stain on leaves and containers, making the plants more difficult to sell. Plants show both a reddish brown and a bluish bronze coating when overhead irrigated.

COURTESY OF TED BILDERRACK

• Chloride

Though not usually considered an essential micronutrient, chlorine (as chloride) is needed in small quantities by plants. However, chloride levels greater than 2 meq/L can become a production problem. The principal effect of too much chloride (Cl⁻) is to increase the osmotic potential of the substrate solution, which reduces the availability of water to plants and can lead to wilting. High chloride levels can also lead to Cl toxicity symptoms in container



FOBROKRESS

FOBRO Kulti-Rotor

Bed shaper/former
Best soil preparation
for best results in one
single pass. Available with
optional Fertilizer spreader
It's a real time saver.




FOBRO Super Max

Bed lifter/shaker
Bare root lifting/digging of
plants is our area of expertise
and it's here we excel.
Let us explain why our blades
(shares) move back and forth.



KRESS Fingerweeder

Hoeing inside the plant
row is possible.
Different degrees of
hardness for different
cultures and soil.



FOBRO Oscillator

Side lifter/shaker
At roughly 10% the cost
of a crawler we dig without
breaking the crowns of your
plants.



For more information:

Call Toll-Free
1-877-GO-FOBRO
(1-877-463-6276)

Bärtschi-FOBRO, LCC,
1715 Airpark Drive, Grand Haven, MI 49417
Phone: (616) 847-0300, Fax (616) 842-1768
or see: www.fobro.com

production. When Cl is taken up by plant roots, it is transported to leaves, where Cl accumulates. Some species, such as roses, azaleas, camellias and rhododendrons, develop leaf edge burn, leaf necrosis and leaf abscission when too much chloride is accumulated. Dilution using an alternative water source is the best method to reduce high chloride levels problems in water. Reverse osmosis can also be used, especially for propagation and salt sensitive crops.

• **Iron and iron bacteria**

A high iron concentration in irrigation water can lead to aesthetic and nuisance problems. Overhead irrigation with water containing 0.5 ppm (mg/L) or more of iron frequently results in a red-brown stain on leaves and containers, making the plants more difficult to sell. Iron concentrations above 0.3 ppm (mg/L), and the resulting oxidation of iron by bacteria, can plug small-orifice emitters used for drip irrigation. Well-water containing iron can be pumped into irrigation basins and some of the iron will settle out.

However, the presence of iron-fixing bacteria can confound iron-related problems. Iron bacteria occur naturally in the soil and can be a problem in well and surface irrigation sources. In wells, iron bacteria often plug submersible pumps and cause them to fail. In surface irrigation basins, an oily sheen over the surface of the water is frequently due to iron bacteria. Iron bacteria keep the iron in the water from settling out. Plants show both a reddish brown and a bluish bronze coating when overhead irrigated (photo, opposite).

Growers can avoid or reduce the problem of iron deposits by making sure that pump intakes are 18 to 30 inches (45 to 75 cm) below the surface of the water, but well above the bottom of the water basin. Pump intakes too close to the bottom of the basin pull iron sediment off the bottom. If adjusting the intake is not possible, the other choices are more expensive.

The first step is to have the water analyzed at a laboratory. A foliar sample from coated plants is also useful in determining how much iron residue is deposited on the plants. If the iron content is high enough to cause problems, an aeration pump can be placed within approximately 50 feet (15 m) of the pump intake. The aeration pump will directly aerate iron, reducing the amounts available for reduction by iron bacteria. The wave action of the pump also helps keep algae and iron bacteria

pushed away from the irrigation pump intake. If aeration is ineffective, iron can be removed through chemical injection and subsequent filtration.

No matter where you are located in the country, high quality water is extremely important for the production of nursery crops. If you have not checked your water lately, now might be a good time to send in water samples for in-depth testing and to decide who on your nursery will do the weekly/monthly water and substrate testing. A simple on-farm testing program can easily save tens of thousands of dollars

by increasing plant growth and preventing problems.

Dr. Ted Bilderback is professor and director of the JC Raulston Arboretum at North Carolina State University, Raleigh, where he has been a member of the horticultural science department since 1977. He can be reached at ted_bilderback@ncsu.edu. Dr. John Dole is a professor and interim department head of the NCSU horticultural science department; he can be reached at john_dole@ncsu.edu. Dr. Ronald Sneed is NCSU professor emeritus of biological and agricultural engineering; he can be reached at sneed@bae.ncsu.edu.



Order Dianthus and Phlox NOW!

Dianthus

Featuring PlantHaven varieties

- Dessert Series
- Star Series
- Devon Cottage
- **NEW** Scent First™


Ask about Firewitch and Frosty Fire and many other varieties!

10 Acres of stock

sizes offered • 200 • 162 • 128 • 72 • 58

Phlox subulata

- Amazing Grace
- Candystripe
- Coral Eye
- Crimson Beauty
- Drummons Pink
- Emerald Blue
- Emerald Pink
- Fort Hill
- McDaniels Cushion
- Millstream Daphne
- Purple Beauty
- Red Wing
- Ronsdorfer Beauty
- Scarlet Flame
- White Delight



For availability and our Broker Network visit
northwesthort.com
800/459-3142